



链滴

【系统命令】ubuntu-18.04 设置开机启动脚本

作者: [moonce](#)

原文链接: <https://ld246.com/article/1540215478973>

来源网站: [链滴](#)

许可协议: [署名-相同方式共享 4.0 国际 \(CC BY-SA 4.0\)](#)

ubuntu-18.04 设置开机启动脚本

作者: [Moonce](#)

1、建立rc-local.service文件

```
sudo vi /etc/systemd/system/rc-local.service
```

2、将下列内容复制进rc-local.service文件

```
[Unit]
```

```
Description=/etc/rc.local Compatibility
```

```
ConditionPathExists=/etc/rc.local
```

```
[Service]
```

```
Type=forking
```

```
ExecStart=/etc/rc.local start
```

```
TimeoutSec=0
```

```
StandardOutput=tty
```

```
RemainAfterExit=yes
```

```
SysVStartPriority=99
```

```
[Install]
```

```
WantedBy=multi-user.target
```

3、创建文件rc.local

```
sudo vi /etc/rc.local
```

4、将下列内容复制进rc.local文件

```
#!/bin/sh -e
```

```
#
```

```
# rc.local
```

```
#
```

```
# This script is executed at the end of each multiuser runlevel.
```

```
# Make sure that the script will "exit 0" on success or any other
```

```
# value on error.
```

```
#
```

```
# In order to enable or disable this script just change the execution
```

```
# bits.
```

```
#
```

```
# By default this script does nothing.
```

```
echo "看到这行字，说明添加自启动脚本成功。" > /usr/local/test.log
```

exit 0

5、给rc.local加上权限

```
sudo chmod +x /etc/rc.local
```

6、启用服务

```
sudo systemctl enable rc-local
```

7、启动服务并检查状态

```
sudo systemctl start rc-local.service  
sudo systemctl status rc-local.service
```

8、重启并检查test.log文件

```
cat /usr/local/test.log
```

如果能看到内容，说明设置成功，你就可以通过编辑rc.local文件来设置启动脚本了

转载自：<https://www.cnblogs.com/airdot/p/9688530.html>