



链滴

程序都嘶叫起来了。uWSGI worker 1 screams: UAAAAAAAAH my master disconnected: i will kill myself !!!

作者: [zonghua](#)

原文链接: <https://ld246.com/article/1459827839172>

来源网站: 链滴

许可协议: [署名-相同方式共享 4.0 国际 \(CC BY-SA 4.0\)](#)

supervisor + uwsgi

```
*** Operational MODE: preforking ***
WSGI app 0 (mountpoint='') ready in 1 seconds on interpreter 0x24ec4e0 pid: 4274 (default a
p)
*** uWSGI is running in multiple interpreter mode ***
gracefully (RE)spawned uWSGI master process (pid: 4274)
spawned uWSGI worker 1 (pid: 4348, cores: 1)
spawned uWSGI worker 2 (pid: 4349, cores: 1)
spawned uWSGI worker 3 (pid: 4350, cores: 1)
spawned uWSGI worker 4 (pid: 4351, cores: 1)
Mon Apr  4 11:29:32 2016 - uWSGI worker 1 screams: UAAAAAAH my master disconnected: i
will kill myself !!!
Mon Apr  4 11:29:32 2016 - uWSGI worker 2 screams: UAAAAAAH my master disconnected: i
will kill myself !!!
```

执行命令重启

```
sudo supervisorctl start demo
demo: ERROR (abnormal termination)
```

uwsgi.log 可能是重启的时候 uwsgi 进程仍在监听该端口

probably another instance of uWSGI is running on the same address (127.0.0.1:8001).
bind(): Address already in use [core/socket.c line 769]

我的配置文件 uwsgi.ini

```
[uwsgi]
# Django-related settings
chdir      = /home/www/Documents/demo
module     = demo.wsgi:application
env        = DJANGO_SETTINGS_MODULE=demo.settings_production
home       = /home/www/Documents/demo/venv
user       = www
uid        = www
pcre-jit
thunder-lock
enable-threads
master     = true
touch-reload = /home/www/Documents/demo/reload
processes  = 4
socket     = 127.0.0.1:8001
chmod-socket = 664
vacuum     = true
```

supervios conf

```
[program:vblue]
directory= /home/www/Documents/demo
```

```
command = /home/www/Documents/demo/venv/bin/uwsgi --ini /home/www/Documents/d  
mo/uwsgi.ini  
autostart=true  
autorestart=true  
redirect_stderr = true  
stdout_logfile = /home/www/Documents/demo/logs/out.log  
stdout_logfile_maxbytes = 1MB  
stderr_logfile= /home/www/Documents/demo/logs/err.log
```

不知道怎么重启的时候关掉 uwsgi 进行监控， 官方文档只有推荐用 Circus

