

Oracle 中查看所有表和字段以及表注释. 字段注释

作者: [kenan](#)

原文链接: <https://ld246.com/article/1489568548072>

来源网站: [链滴](#)

许可协议: [署名-相同方式共享 4.0 国际 \(CC BY-SA 4.0\)](#)

<p>获取表: </p>

```
<pre class="brush: sql">select table_name from user_tables; //当前用户拥有的表
```

```
<p>select table_name from all_tables; //所有用户的表<br>
```

```
select table_name from dba_tables; //包括系统表<br>
```

```
select table_name from dba_tables where owner='用户名' </pre>
```

```
<p>user_tables: <br>
```

```
table_name,tablespace_name,last_analyzed 等<br>
```

```
dba_tables: <br>
```

```
owner,table_name,tablespace_name,last_analyzed 等<br>
```

```
all_tables: <br>
```

```
owner,table_name,tablespace_name,last_analyzed 等<br>
```

```
all_objects: <br>
```

```
owner,object_name,subobject_name,object_id,created,last_ddl_time,timestamp,status 等<br><br>
```

```
select * from user_tab_columns where Table_Name='用户表';<br>
```

```
select * from all_tab_columns where Table_Name='用户表';<br>
```

```
select * from dba_tab_columns where Table_Name='用户表';<br>
```

```
user_tab_columns: <br>
```

```
table_name,column_name,data_type,data_length,data_precision,data_scale,nullable,column_id  
等<br>
```

```
all_tab_columns : <br>
```

```
owner,table_name,column_name,data_type,data_length,data_precision,data_scale,nullable,colu  
n_id 等<br>
```

```
dba_tab_columns: <br>
```

```
owner,table_name,column_name,data_type,data_length,data_precision,data_scale,nullable,colu  
n_id 等</pre>
```

```
<p>获取表注释: <br><br>
```

```
select * from user_tab_comments<br>
```

```
user_tab_comments: table_name,table_type,comments<br>
```

```
相应的还有 dba_tab_comments, all_tab_comments, 这两个比 user_tab_comments 多了 owner  
。 <br><br>
```

```
获取字段注释: <br><br>
```

```
select * from user_col_comments<br>
```

```
user_col_comments: table_name,column_name,comments</pre>
```

```
<p>相应的还有 dba_col_comments, all_col_comments, 这两个比 user_col_comments 多了 owner  
列。 </pre></pre><p></p>
```

```
<p>&nbsp;</p>
```