



链滴

Linkdood 在线安装

作者: [zhangxinming](#)

原文链接: <https://ld246.com/article/1534742308805>

来源网站: 链滴

许可协议: [署名-相同方式共享 4.0 国际 \(CC BY-SA 4.0\)](#)

一、配置需求

- [【服务器配置需求】](#)

二、准备工作

- 服务器安装CentOS 6.9操作系统, 并配置固定IP地址 < [CentOS 安装手册](#)>
- 拥有root管理员账号, 安装过程必须使用root
- 如果在线安装, 必须确保服务器可以访问互联网

三、在线安装

3.1. 下载安装工具

```
[root@linkdood data]# wget http://www.linkdood.cn/download/standard/tools/install.py
--2018-08-20 13:17:40-- http://www.linkdood.cn/download/standard/tools/install.py
Resolving www.linkdood.cn... 172.16.8.25, 172.16.8.25
Connecting to www.linkdood.cn|172.16.8.25|:80... connected.
HTTP request sent, awaiting response... 200 OK
Length: 46783 (46K) [application/octet-stream]
Saving to: "install.py"
```

```
100%[=====] 46,783 --.-K/s in 0s
```

```
2018-08-20 13:17:40 (96.7 MB/s) - "install.py" saved [46783/46783]
```


3.2. 安装过程

- **执行命令**
在线: `python install.py`
离线: `python install.py -o`
- **语言选择**
输入: cn(中文)、en(英文)
默认: cn(中文)
- **备份重装** <只有安装过服务的才会提示此步>
输入: yes(备份已有服务, 并安装新服务)、no(不重装服务)
默认: no(不重装服务)


```

server-grouppfile STARTING... [ OK ]
server-grouppmember STARTING... [ OK ]
server-grouppverify STARTING... [ OK ]
server-enterpriseregister STARTING... [ OK ]
server-enterpriseuser STARTING... [ OK ]
server-enterpriserolesmenu STARTING... [ OK ]
server-analysiswebsite STARTING... [ OK ]
server-memo STARTING... [ OK ]
server-verifycode STARTING... [ OK ]
server-iosnotice STARTING... [ OK ]
server-task STARTING... [ OK ]
server-emoticon STARTING... [ OK ]
server-operationlog STARTING... [ OK ]
server-platform STARTING... [ OK ]
server-enterprisetaask STARTING... [ OK ]
server-lbs STARTING... [ OK ]
server-commentcenter STARTING... [ OK ]
server-share STARTING... [ OK ]
server-enterprisestatistics STARTING... [ OK ]
server-enterprisechat STARTING... [ OK ]
server-unreadmsgpush STARTING... [ OK ]
server-platformstatistics STARTING... [ OK ]
server-vrvxin STARTING... [ OK ]
server-sharecomment STARTING... [ OK ]
server-cloud STARTING... [ OK ]
server-imuser STARTING... [ OK ]
server-platform-business STARTING... [ OK ]
server-enterpriseorganization STARTING... [ OK ]
TOMCAT STARTING... [ OK ]
TOMCAT STARTING... [ OK ]
loading to java.....
loading to java.....
Starting prelogin [ OK ]
Starting upload [ OK ]
Starting ap [ OK ]
Starting badword [ OK ]
Starting go-mail [ OK ]
Starting apnsAgentConfig [ OK ]
Starting nginx [ OK ]

```



V

< http://172.16.8.68:10077 >
User:admin Password:lw#0uTr.

 ****请确保以上所有状态为【OK】，如有异常请用linkd进行服务管理****

四、Linkd管理工具

- 【linkd使用手册】

五、目录解析

```
/data/linkdood  
|--- im          #程序目录  
|--- data       #数据目录  
|--- logs       #日志目录  
|--- tools      #依赖工具目录
```

六、业务逻辑

- 【Linkdood业务逻辑】